
2025/04/24 02:31 1/4 Windows


Windows


Disable Security Questions Windows 11/10 via Local Group Policy Editor

In case you forget your password



- 1. Press Windows + R key combinations to open the Run window.
- 2. Input gpedit.msc in the text box and press Enter.
- 3. In the left panel, navigate to the following location:
- 4. Computer Configuration > Administrative Templates > Windows Components > Credential User Interface
- 5. In the right panel, double-click Prevent the use of security questions for local accounts.
- 6. In the pop-up window, select the option of Enabled, then click Apply > OK.





Remote Desktop


To enable remote desktop and allow to log in via certain users, follow these steps:

- 1. On the device you want to connect to, select Start and then click the Settings icon on the left.
- 2. Select the System group followed by the Remote Desktop item.
- 3. Use the slider to enable Remote Desktop.
- 4. It is also recommended to keep the PC awake and discoverable to facilitate connections. Click Show settings to enable.
- 5. As needed, add users who can connect remotely by clicking Select users that can remotely access this PC.
- 6. Members of the Administrators group automatically have access.
- 7. Make note of the name of this PC under How to connect to this PC. You'll need this to configure the clients.

Map Network Drives

Mapping with different credentials only stays persistent after restart, if you **select both options the first time** you create the network drive.

2025/04/24 02:31 3/4 Windows



Elevated Programs and Network Drives

One of the useful tools that Windows offers is the ability to assign drive letters to the network locations. You can use the Map Network Drive command of Windows Explorer or AB Commander to create the network drives. After a network drive has been created, you can use it just like any other drive: browse its contents, copy file to or from it, and so on.

A problem may occur, however, if you use Windows Vista or Windows 7 and need to access the network drive from an application that runs elevated (a.k.a. as administrator).

- How to make elevated programs recognize network drives
- create a new DWORD entry with the name EnableLinkedConnections and value 1 in HKEY_LOCAL_MACHINE/SOFTWARE/Microsoft/Windows/CurrentVersion/Policies/Sy stem
- you can do this with this single command (as admin): reg add
 "HKEY_LOCAL_MACHINE\Software\Microsoft\Windows\CurrentVersion\Policies\S
 ystem" /v "EnableLinkedConnections" /t REG_DWORD /d 0x00000001 /f

Last update: 2024/05/27 12:54

From:

https://dokuwiki.hampel-soft.com/ - HAMPEL SOFTWARE ENGINEERING

Permanent link:

https://dokuwiki.hampel-soft.com/kb/common/windows?rev=1716814449

Last update: 2024/05/27 12:54

